

# Radiation Oncology HPC Cluster

## User Guide

- How to access:
  - SSH
    - host: rohpc.swmed.org
    - port:22
  - VNC
    - SSH to rohpc.swmed.org
    - Configure xstartup
    - Vncserver –geometry 1280x768
    - Connect to vnc session using free tightvnc or turbovnc
  - Web
    - <https://rohpc.swmed.org:8081/userportal/#/login>
    - Cluster overview, workload etc...
- Computing resources:
  - “sinfo” to see the partitions(queue) and compute nodes available
    - defq : default queue, 1 compute node: rohpc100: 24C/128GB
    - dgxq: v100 queue: 3 V100 GPU nodes: rodgx101, rodgx102: 8GPU/32GB, 80C/500GB
    - k80q: k80 queue: 1 K80 GPU node: rok8001: 16GPU/16GB
    - titansq: titans queue: 2 Titans nodes: rotitans[009-010]: 4GPU/6GB
    - mem192: 3 compute nodes : rohpc101, rohpc102, rohpc103: 24C/192GB
    - mem384: 2 compute nodes : rohpc301, rohpc302: 24C/384GB
    - \*future GPU nodes: titans1-8 (16GPU/16GB)
  - scontrol show nodes to see further details
- Data storage:
  - **Avoid** storing any data in:
    - /home
      - 2 TB capacity, daily snapshot, no backup
  - When storing data you can use
    - /data, /apps
      - 46 TB capacity, daily snapshot, no backup
    - **(NOT READY YET)** /archive
      - TBD capacity, mount from Research Storage >400TB
  - When running GPU jobs, can temporarily use the storage available below to save models
    - /rodgx101fs
      - 7 TB capacity, no snapshot, no backup
    - /rodgx102fs
      - 7 TB capacity, no snapshot, no backup
  - In the /data, /archive, /rodgx101fs, and /rodgx101fs, there is a folder hierarchy, so please make your user folder inside the “maia” folder.
- Using slurm:
  - slurm is the scheduler used on the hpc
  - <https://slurm.schedmd.com/documentation.html>
  - Submit jobs with slurm:
    - Examples in /apps/slurm-test: defq-test, dgxq-test, mem192q-test, mem384q-test

- cat test-jobs.sh
- ./test-jobs.sh
- GPU run example:
  - You have a “helloworld.py” python file you want to run. Let’s say it requires CUDA 10.1 and cudnn 7.6. You make a .sh file (let’s call it “helloworld.sh”), with the following lines:

```
#!/bin/bash
#
#SBATCH --job-name=helloworld
#SBATCH --output=helloworld.txt
#
#SBATCH --partition=dgxq
#SBATCH --gres=gpu:dgx:1
#
#SBATCH --ntasks=1
#SBATCH --time=20:00:00
#SBATCH --mem-per-cpu=64

module load cuda10.1/profiler/10.1.243
module load cuda10.1/toolkit/10.1.243
module load cuda10.1/blas/10.1.243
module load cuda10.1/fft/10.1.243
module load cuda10.1/nsight/10.1.243

module load cudnn7.6-cuda10.1/7.6.5.32

srun python helloworld.py
```

- - This particular setup is asking for 1 GPU on the dgx partition. The maximum runtime here is 20 hours, with 64 GB max memory per cpu.
      - Note: the higher resources you request, the lower your priority
    - “module load” allows you to customize your environment as needed. You can run “module avail” to see what is available to use.
  - You can then queue the slurm scheduler with
    - sbatch helloworld.sh
    - Note: you need to be in a python/conda environment when you queue for it to recognize the .py file properly
- SBGRID : Mount from BioHPC
  - <https://portal.biohpc.swmed.edu/content/cloud-services/sbgrid/>
  - SBGrid Software Suite contains 400+ scientific software applications
  - <https://sbgrid.org>
  - add . /programs/sbgrid.shrc
  - require VNC session
  - example application tested : ccp4i, maestro
- Docker:
  - Docker is installed on all the CPU nodes: rohpc100-rohpc103, rohpc301-302
  - If you plan to run docker on these nodes, your id must be added to the docker group
  - Example:
    - ssh [myid@rohpc.swmed.org](mailto:myid@rohpc.swmed.org)
    - >ssh myid@rohpc301
    - >module load docker
    - >docker pull hello-world
    - >docker run hello-world